

openWRT (Wireless) Repeater

/etc/config/network

```
config 'switch' 'eth0'
    option 'enable' '1'
config 'switch_vlan' 'eth0_0'
    option 'device' 'eth0'
    option 'vlan' '0'
    option 'ports' '0 1 2 3 5'
config 'switch_vlan' 'eth0_1'
    option 'device' 'eth0'
    option 'vlan' '1'
    option 'ports' '4 5'
config 'interface' 'loopback'
    option 'ifname' 'lo'
    option 'proto' 'static'
    option 'ipaddr' '127.0.0.1'
    option 'netmask' '255.0.0.0'
config 'interface' 'lan'
    option 'type' 'bridge'
    option 'ifname' 'eth0.0'
    option 'proto' 'static'
    option 'netmask' '255.255.255.0'
    option 'ipaddr' '192.168.0.1'
config 'interface' 'wan'
    option 'ifname' 'eth0.1'
    option 'proto' 'dhcp'
config 'interface' 'wwan'
    option 'proto' 'dhcp'
```

/etc/config/wireless

```
config 'wifi-device' 'wl0'
    option 'type' 'broadcom'
    option 'txpower' '18'
    option 'hwmode' '11bg'
    option 'channel' '11'
config 'wifi-iface'
    option 'ssid' 'f00b4r'
    option 'device' 'wl0'
    option 'mode' 'sta'
    option 'network' 'wwan'
    option 'key' '(4xx3ss-2-the-d0me)'
    option 'encryption' 'psk2+tkip+ccmp'
config 'wifi-iface'
    option 'device' 'wl0'
    option 'mode' 'ap'
```

```
option 'encryption' 'none'  
option 'ssid' 'OpenWrt-Repeater'  
option 'network' 'lan'
```

/etc/config/dhcp

```
cconfig dnsmasq  
option domainneeded 1  
option boguspriv 1  
option filterwin2k 0 # enable for dial on demand  
option localise_queries 1  
option rebind_protection 1 # disable if upstream must serve RFC1918  
addresses  
option rebind_localhost 1 # enable for RBL checking and similar  
services  
#list rebind_domain example.lan # whitelist RFC1918 responses for  
domains  
option local '/lan/'  
option domain 'lan'  
option expandhosts 1  
option nonegcache 0  
option authoritative 1  
option readethers 1  
option leasefile '/tmp/dhcp.leases'  
option resolvfile '/tmp/resolv.conf.auto'  
#list server '/mycompany.local/1.2.3.4'  
#option nonwildcard 1  
#list interface br-lan  
#list notinterface lo  
#list bogusnxdomain '64.94.110.11'  
config dhcp lan  
option interface lan  
option start 100  
option limit 150  
option leasetime 12h  
config dhcp wan  
option interface wan  
option ignore 1
```

/etc/config/firewall

```
config 'defaults'  
option 'syn_flood' '1'  
option 'input' 'ACCEPT'  
option 'output' 'ACCEPT'  
option 'forward' 'REJECT'  
config 'zone'  
option 'name' 'lan'  
option 'network' 'lan'
```

```
option 'input' 'ACCEPT'
option 'output' 'ACCEPT'
option 'forward' 'REJECT'
config 'zone'
option 'name' 'wan'
option 'input' 'REJECT'
option 'output' 'ACCEPT'
option 'forward' 'REJECT'
option 'masq' '1'
option 'mtu_fix' '1'
option 'network' 'wan wwan'
config 'forwarding'
option 'src' 'lan'
option 'dest' 'wan'
config 'rule'
option 'name' 'Allow-DHCP-Renew'
option 'src' 'wan'
option 'proto' 'udp'
option 'dest_port' '68'
option 'target' 'ACCEPT'
option 'family' 'ipv4'
config 'rule'
option 'name' 'Allow-Ping'
option 'src' 'wan'
option 'proto' 'icmp'
option 'icmp_type' 'echo-request'
option 'family' 'ipv4'
option 'target' 'ACCEPT'
config 'rule'
option 'name' 'Allow-DHCPv6'
option 'src' 'wan'
option 'proto' 'udp'
option 'src_ip' 'fe80::/10'
option 'src_port' '547'
option 'dest_ip' 'fe80::/10'
option 'dest_port' '546'
option 'family' 'ipv6'
option 'target' 'ACCEPT'
config 'rule'
option 'name' 'Allow-ICMPv6-Input'
option 'src' 'wan'
option 'proto' 'icmp'
list 'icmp_type' 'echo-request'
list 'icmp_type' 'destination-unreachable'
list 'icmp_type' 'packet-too-big'
list 'icmp_type' 'time-exceeded'
list 'icmp_type' 'bad-header'
list 'icmp_type' 'unknown-header-type'
list 'icmp_type' 'router-solicitation'
list 'icmp_type' 'neighbour-solicitation'
option 'limit' '1000/sec'
```

```
option 'family' 'ipv6'  
option 'target' 'ACCEPT'  
config 'rule'  
option 'name' 'Allow-ICMPv6-Forward'  
option 'src' 'wan'  
option 'dest' '*'  
option 'proto' 'icmp'  
list 'icmp_type' 'echo-request'  
list 'icmp_type' 'destination-unreachable'  
list 'icmp_type' 'packet-too-big'  
list 'icmp_type' 'time-exceeded'  
list 'icmp_type' 'bad-header'  
list 'icmp_type' 'unknown-header-type'  
option 'limit' '1000/sec'  
option 'family' 'ipv6'  
option 'target' 'ACCEPT'  
config 'include'  
option 'path' '/etc/firewall.user'
```

Troubleshooting

1. What if openWRT constantly disconnects from the host access point?

This might be related to the fact, that your access points uses the same ESSID on the 2.4GHz as 5GHz channel. The fix is either to disable one of them on your host AP, reconnect 'til it works or check for another openWRT version for your device.

It might also be that the openWRT wireless host is not on the same channel as the host AP.

1. The 'Associated Stations' shows a '?' below the IP Address field of an entry.

Looks like a bug in the openWRT GUI. Ignore it an verify it via ssh on the access point.

From:
<https://wiki.c3l.lu/> - **Chaos Computer Club Lëtzebuerg**

Permanent link:
<https://wiki.c3l.lu/doku.php?id=projects:howtos:openwrt-repeater&rev=1436402235>

Last update: **2015/07/15 21:54**

